

 In the previous lecture, we started talking about ECG and we discussed the bipolar limb leads, in this lecture we'll learn how to record the positive recording in those leads.

Bipolar Limb Leads

• Lead I

- We said that the mean electrical axis of QRS is pointing to the left, inferiorly and anteriorly.
- In recording limb lead I, the negative terminal of the electrocardiograph is connected to the right arm and the positive terminal is connected to the left arm, so the axis of lead 1 will be directed from the right arm to the left arm
- In order to record the value of lead I we draw a perpendicular angle from the mean electrical axis to the axis of lead I and this will be the recording of the QRS in lead I
- When the point where the right arm connects to the chest is electronegative with respect to the point where the left arm connects, the electrograph records positively, when the opposite is true it records negatively.
- For better understanding, let's take a numerical example. Let us assume that momentarily, the right arm is -0.2 millivolts (negative) and the left arm is +0.3 millivolts (positive), and the left leg is +1.0 millivolts (positive). Lead I records a positive potential of +0.5 millivolts because this is the difference between the -0.2 millivolts on the right arm and the +0.3 millivolts on the left arm.

• Lead II

- In recording limb lead II, the negative terminal of the electrodiograph is connected to the right arm and the positive terminal is connected to the left leg
- We record the value of Lead II in the same way we calculated the value of Lead I by drawing a perpendicular angle
- When the right arm is negative with respect to the left leg, LL the electrodiograph records positively, when the opposite is true it records negatively
- Going back to our numerical example, lead II records a positive potential of +1.2 millivolts because these are the instantaneous potential differences between the respective pairs of limbs.





• Lead III

- To record Lead III, the negative terminal of the electrodiograph is connected to the left arm and the positive terminal is connected to the left leg
- Just like we did before, we record its value by drawing a perpendicular angle
- When the left arm is negative with respect to the left leg it records positively, when the opposite is true it records negatively
- As for the above-mentioned example, lead III records a positive potential of +0.7 millivolts as these are the instantaneous potential differences between the respective pairs of limbs.

-From the three leads, it is clear that lead II contributes the most to the resultant vector (as it is parallel to it) so it will have the highest magnitude.

-You can get the mean electrical axis by drawing a perpendicular line from every lead's axis and these three lines should meet in the middle in one point and this is the mean electrical value.

- The following figure represents the recording of the mean QRS in every lead, we calculate the mean QRS by algebraic summation (it is done by the summation of the small squares)
- You can notice that lead II is equal to lead I + lead III and this is called <u>Einthoven's law</u>
- By drawing the axis of each lead you'll end up with an equilateral, equiangular triangle (each angle is 60 degrees)
- The heads of this triangle are between the right arm, left arm and left foot, with the heart being at the center
- When you draw a perpendicular line from the midpoint to the sides you are going to have two equal sides
- We can also convert the information from equilateral triangle to a triaxial reference system, this is done by moving the axis of lead I, II, III in a parallel manner so that they meet at the center
- In the triaxial reference system, each lead is 60 degrees clockwise of the next and we take lead 1 as a reference







*** Augmented Unipolar Limb Leads**

- Another system of leads in wide use is the augmented unipolar limb lead. In this type of recording we connect on the **negative** electrode
- three connections on the same exact positions where we put the Bipolar Limb Leads (right arm, left arm and left foot). These connections have Very High Resistance (=5000 Ohms) so that the net current in these three connections will be ZERO (called **indifferent** electrode).
- Note that all three connections are considered one negative electrode
- Then we place the positive electrode on a different position (Right Arm, Left Arm and Left Foot) each at a time calculating (VR, VL, and VF, respectively). The electrode is called **exploring** electrode.



- The problem with the above-mentioned experiment is that the recording was too small, so a scientist called Wilson removed the high resistance from the right arm and kept the high resistance in the other two limbs.
- After removing the high resistance connected to the right limb, he found that the recording was augmented (amplified) which was way better to calculate. He called the new recording aVR (augmented vector right arm).
- He did the same with the left arm and got an augmented record and called it (aVL), and the same with the left foot and got another augmented record and called it (aVF).
- ➔ To summarize, in this type of recording, two of the limbs are connected through electrical resistances to the negative terminal of the electrocardiograph, and the third limb is connected to the positive terminal.

	Indifferent Electrode	Exploring Electrode
aVR	Connected to the left arm and left foot	Connected to the right arm
aVL	Connected to the right arm and left foot	Connected to the left arm
aVF	Connected to the right and left arms	Connected to the left foot

- It is called unipolar limb leads because we connect one pole to each of these limbs
- The mean electrical axis records positive if it's going towards the positive electrode, and negative if it is going away from the positive electrode

- aVR:
 - aVR = (LA-LL) vs. RA (+)
 - The measured potential difference is between RA (+) and the center point between LA and LL (-)
 - If we put the positive electrode in the right arm, aVR will move in opposite direction to the mean electrical axis so recording will be negative
- aVL:
 - aVL = (RA-LL) vs. LA (+)
- The measured potential difference is between LA (+) and the center point between RA and LL (-)
- If we put the positive electrode in the left arm, aVL will move in the same direction to the mean electrical axis so recording will be positive (even though it's small, it records positively)
- aVF:
 - aVF = (RA-LA) vs. LL (+)
 - The measured potential difference is between LL (+) and the center point between RA and RA (-).
 - If we put the positive electrode in the left foot, aVF will move in the same direction to the mean electrical axis so the recording will be highly positive (most positive)
- → Let's summarize using the following figure. aVR is negative because we are going away from the positive electrode, aVL is positive but in a small record and aVF is highly positive because it's mean electrical axis is going towards the positive electrode in the left foot.

RA

LL

LL



- In the limb leads we looked at the activity of the heart from the frontal plane, however using the Chest leads we will look at it from the horizontal plane.
- There are 6 unipolar chest leads (V1,V2,V3,V4,V5,V6) or we can call them (C1,C2,C3,C4,C5,C6).

Chest Lead	Location	
V1	in the 4 th intercostal space (right side) just beside the sternum	
V2	in the 4 th intercostal space (left side) around the sternum	
V3	in the mid-way between V2 and V4	
V4	in the 5 th intercostal space (<mark>left</mark> side) in the mid-clavicular line	
V5	in the 5 th intercostal space in the anterior axillary line	
V6	in the 5 th intercostal space in the mid axillary line	

 The following graph represents precordial (chest leads): indifferent electrode (RA-LA-LL) vs. chest lead moved from position V1 through position V6:



- The direction of the mean electrical axis is in V1 and V2 is away from the V_1 V_2 V_3 V_4 V_5 V_5 positive electrode so as we can see in this graph V1 and V2 are recorded negative
- V3 is recorded in the middle between positive and negative
- The direction of the mean electrical axis in V4 and V5 and V6 is toward the positive electrode so they're recorded positive
- Chest leads are very sensitive to electrical potential changes underneath the electrode
- Chest leads are considered unipolar leads



ightarrow In conclusion, we have 12 leads, 9 of them are unipolar and 3 of them are bipolar

 The chest leads are from the <u>transverse plane</u> whereas the bipolar limb leads and the augmented unipolar leads are from the <u>frontal plane</u>.

- The following figure presents a complete ECG (12 leads recording), as you can see:
- The QRS in lead II equals the QRS in both lead I and lead III
- aVR is negative whereas avF and aVL are positive
- V1 and V2 are negative and V3 is starting to be positive (midline)
- V4, V5, V6 are positive



- Chest leads are placed anteriorly on the chest, they can tell you about what is happening in the anterior and inferior aspects of the heart, but they can't tell you about the changes in the posterior aspect of the heart. To inspect the posterior aspect of the heart, we use another type of electrode that's called esophageal electrode.
- You use esophageal lead if you have a suspicion that there might be something abnormal in the posterior surface of the heart. Esophageal lead is used by putting the exploring electrode in the esophagus through the larynx → throat → esophagus and you start recording when it becomes posterior to the heart.

• The following pictures are for further understanding:

